

Last update: 2025/01/10

www.softbase.co.kr
Copyright © SOFTBase Inc. All rights reserved.

.....	1
.....	1
.....	1

xFrame5

- xFrame5가 (SSO) xFrame5 CORS()
- xFrame5 "A" xFrame5 "B" ?
- xadmin 가 ?
- xFrame5 404 Not Found 가 . MIMEType
- JEU Servlet hasn't read all of the HTTP body 가 ?
- TOMCAT org.json.simple.JSONValue.parse 가 ?

xFrame5가 (SSO) CORS() ?
 .html "xframe_screen_mainframe" " 1 " 가

xFrame5 "A" xFrame5 "B" ?
 "B" 가 .html "xframe_screen_mainframe" " 1 " 가

xadmin 가 ?

xadmin xFrame5 UI .

xFrame5 404 Not Found 가 . MIMEType 가 ?

xFrame5 MIMEType .
 webtob



- lst mimeType = "text/plain", SvrType = HTML
- xstl mimeType = "text/plain", SvrType = HTML
- pic mimeType = "text/plain", SvrType = HTML

TOMCAT

```

<mime-mapping>
  <extension>xstl</extension>
  <mime-type>text/plain</mime-type>
</mime-mapping>
<mime-mapping>
  <extension>lst</extension>
  <mime-type>text/plain</mime-type>
</mime-mapping>
<mime-mapping>
  <extension>pic</extension>
  <mime-type>text/plain</mime-type>
</mime-mapping>

```



JEUS Servlet hasn't read all of the HTTP body 가 ?



JEUS webtob connector postdata read timeout

JEUS postdata-read-timeout

- : WEBMain.xml
- XML: <jeus-system><web-container><context-group><webserver-connection><webtob-listener><postdata-read-timeout>
- : postdata read timeout Web post-data
- : millisecond value
- : 30000

webtob

- HTTP 가 Request Body
- 0
- default 0 bytes



TOMCAT org.json.simple.JSONValue.parse 가

?

maxPostSize maxParameterCount 0
maxPostSize



- The maximum size in bytes of the POST which will be handled by the container FORM URL parameter parsing.
- The limit can be disabled by setting this attribute to a value less than or equal to 0.
- If not specified, this attribute is set to 2097152 (2 megabytes.)

maxParameterCount

- The maximum number of parameter and value pairs (GET plus POST) which will be automatically parsed by the container.
- Parameter and value pairs beyond this limit will be ignored.
- A value of less than 0 means no limit. If not specified, a default of 10000 is used.
- Note thatFailedRequestFilter filter can be used to reject requests that hit the limit.)

From:

<https://technet.softbase.co.kr/wiki/> - **xFrame5 TechNet**

Permanent link:

https://technet.softbase.co.kr/wiki/qna/qna_admin



Last update: **2025/01/10 14:32**