

가

Last update: 2024/03/13

www.softbase.co.kr
Copyright © SOFTBase Inc. All rights reserved.



가	1
	1
	1

가

xFrame5

: /HTML5/UTIL/RWD/rwdview_basic

- [rwdview_basic.xml](#)
- [rwdview_basic.js](#)
- [...](#)

```
function screen_on_load()
{
    this.cbo_device_on_itemchange();
}

// "
function fld_url_on_keydown(objInst, keycode, bctrldown, bshiftdown,
baltdown, bnumpadkey)
{
    // ENTER          btn_go_on_click
    if (keycode == 13) { this.btn_go_on_click(); }
    return 0;
}

// "
function btn_go_on_click(objInst)
{
    var url = this.fld_url.gettext();

    //      xFrame5                      가          가
    if (url.indexOf("?") < 0) { url += "?xframe_screen_mainframe=1"; }
    else { url += "&xframe_screen_mainframe=1"; }

    this.web.seturl(url);
}

// "
function btn_rotate_on_click(objInst)
{
```

```
    this.web.setsize(this.web.getheight(), this.web.getwidth());  
  
    //      /  
    this.SetSplitterSizePos();  
}  
  
//      /  
function SetSplitterSizePos()  
{  
    //  
    this.DisplayWebSize();  
  
    //      /  
    this.spl_vert.setwidth(this.web.getwidth());  
    this.spl_vert.settop(this.web.gettop() + this.web.getheight() + 6);  
  
    //      /  
    this.spl_horz.setheight(this.web.getheight());  
    this.spl_horz.setleft(this.web.getleft() + this.web.getwidth() + 6);  
}  
  
//  
function DisplayWebSize()  
{  
    var border_size_sum = 2;  
  
    //  
    this.fld_width.settext(this.web.getwidth() - border_size_sum);  
    this.fld_height.settext(this.web.getheight() - border_size_sum);  
}  
  
// "  
function btn_setsize_on_click(objInst)  
{  
    var border_size_sum = 2;  
  
    //  
    this.web.setsize(parseInt(this.fld_widthgettext(), 10) +  
border_size_sum,  
                    parseInt(this.fld_heightgettext(), 10) +  
border_size_sum);  
  
    //      /  
    this.SetSplitterSizePos();  
}  
  
// "  
function cbo_device_on_itemchange(objInst, nprev_item, ncur_item,  
event_type)  
{  
    var code;  
  
    //
```

```
code = this.cbo_device.val();  
  
//           /  
size_arr = code.split("X");  
  
//  
this.fld_width.settext(size_arr[0]);  
this.fld_height.settext(size_arr[1]);  
  
//  
this.btn_setsize_on_click();  
}  
  
//  
function spl_horz_on_moveend(objInst, nStartPos, nPos, nMoveGap)  
{  
//  
this.DisplayWebSize();  
}  
  
//  
function spl_vert_on_moveend(objInst, nStartPos, nPos, nMoveGap)  
{  
//  
this.DisplayWebSize();  
}  
  
// "  
function btn_zoom_on_click(objInst)  
{  
var browser_window;  
  
//           /  
browser_window = this.web.getbrowserwindow();  
if (browser_window && browser_window.screen &&  
browser_window.screen.setzoom) {  
    browser_window.screen.setzoom(this.fld_zoom.gettext());  
}  
}  
  
// "  
function fld_zoom_on_keydown(objInst, keycode, bctrldown, bshiftdown,  
baltdown, bnumpadkey)  
{  
// ENTER      btn_zoom_on_click  
if (keycode == 13) { this.btn_zoom_on_click(); }  
return 0;  
}
```

From:
<https://technet.softbase.co.kr/wiki/> - xFrame5 TechNet

Permanent link:
https://technet.softbase.co.kr/wiki/guide/util/rwd/rwdview_basic

Last update: 2024/03/13 09:37