

# 가

Last update: 2023/12/11

가	1
.....	1
.....	1

# 가

linenumber\_show, linenumber\_title, linenumber\_width, linenumber\_resizable .

API getlinenumbershow, setlinenumbershow, getlinenumberwidth, setlinenumberwidth .

API getlinenumberresizable, setlinenumberresizable .

EVENT on\_headerclick, on\_itemclick, on\_statitemclick .

: /HTML5/COMPONENT/GRID/grid\_linenumber\_basic

- [grid\\_linenumber\\_basic.xml](#)
- [grid\\_linenumber\\_basic.js](#)
- [grid\\_linenumber\\_basic.css](#)

```
// "setlinenumbershow"
function btn_setlinenumbershow_on_mouseup(objInst)
{
    //
    this.grd.setlinenumbershow(!this.grd.getlinenumbershow());
}

// "setlinenumberbackcolorex"
function setlinenumberbackcolorex_on_mouseup(objInst)
{
    //
    this.grd.setlinenumberbackcolorex(1, factory.rgb(255, 0, 0));
}

// "setlinenumbertitle"
function setlinenumbertitle_on_mouseup(objInst)
{
    //
    this.grd.setlinenumbertitle(this.grd.getlinenumbertitle() + "*");
}
```

```
// "setlinewidthwidth"
function btn_setlinewidthwidth_on_mouseup(objInst)
{
    //          10 가
    this.grd.setlinewidthwidth(this.grd.getlinewidthwidth() + 10);
}

// "setlinenumberresizable"
function btn_setlinenumberresizable_on_mouseup(objInst)
{
    //          가
    this.grd.setlinenumberresizable(!this.grd.getlinenumberresizable());
}

//          -1
function grd_on_headerclick(objInst, nHeaderRow, nHeaderCol)
{
    if (nHeaderCol == -1) {
        screen.alert("          , = -1, = " + nHeaderRow);
    }
}

//          -1
function grd_on_itemclick(objInst, nClickRow, nClickColumn, bBtnClick,
nImgIndex, strImgUrl)
{
    if (nClickColumn == -1) {
        screen.alert("          , = -1, = " + nClickRow);
    }
}

//          -1
function grd_on_statitemclick(objInst, nStatRowFlag, nStatColumnFlag, nRow,
nColumn)
{
    if (nColumn == -1) {
        screen.alert("          , = -1, = " + nRow);
    }
}
}
```

From:  
<https://technet.softbase.co.kr/wiki/> - xFrame5 TechNet

Permanent link:  
[https://technet.softbase.co.kr/wiki/guide/component/grid/grid\\_linenumber\\_basic](https://technet.softbase.co.kr/wiki/guide/component/grid/grid_linenumber_basic)



Last update: 2023/12/11 16:01