

가

Last update: 2023/08/08

가	1
.....	1
.....	1

가

screen messagebox API
 screen on_messagebox
 screen messageboxsync
API

ANIMATE_TYPE_MESSAGEBOX

: /HTML5/SCREEN/SCREEN/screen_messagebox

- [screen_messagebox.xml](#)
- [screen_messagebox.js](#)
- [screen_messagebox.js](#)

```
//
function GetMessageBoxType(messagebox_result)
{
    var messagebox_result_type;

    messagebox_result_type = "";
    switch (messagebox_result) {
        case XFD_MB_RESOK: messagebox_result_type = "OK"; break;
        case XFD_MB_RESCANCEL: messagebox_result_type = "CANCEL"; break;
        case XFD_MB_RESABORT: messagebox_result_type = "STOP"; break;
        case XFD_MB_RESRETRY: messagebox_result_type = "RETRY"; break;
        case XFD_MB_RESIGNORE: messagebox_result_type = "IGNORE"; break;
        case XFD_MB_RESYES: messagebox_result_type = "YES"; break;
        case XFD_MB_RESNO: messagebox_result_type = "NO"; break;
        case XFD_MB_RESCONTINUE: messagebox_result_type = "CONTINUE"; break;
    }
}
```

```

        default: messagebox_result_type = "UNKNOWN"; break;
    }

    return messagebox_result_type;
}

/**
 *     messagebox API
 *
 * @param {string} messagebox_id      ID
 * @param {number} result            가
 */
function screen_on_messagebox(messagebox_id, result)
{
    factory.consoleprint("on_messagebox> start");
    factory.consoleprint("on_messagebox> messagebox_id = " + messagebox_id);
    factory.consoleprint("on_messagebox> result = " + result);
    factory.consoleprint("on_messagebox> messagebox_result_type = " +
this.GetMessageBoxType(result));
}

function btn_messagebox_info_on_click(objInst)
{
    //
    screen.messagebox("INFO      ", "INFO      ",
        XFD_MB_INFORMATION, XFD_MB_OK, XFD_MB_FOCUSBUTTON1,
objInst.getname());
}

function btn_messagebox_error_on_click(objInst)
{
    //
    screen.messagebox("ERROR      ", "ERROR      ",
        XFD_MB_ERROR, XFD_MB_OK, XFD_MB_FOCUSBUTTON1, objInst.getname());
}

function btn_messagebox_question_on_click(objInst)
{
    //
    screen.messagebox("QUESTION      ", "QUESTION      ",
        XFD_MB_QUESTION, XFD_MB_OK, XFD_MB_FOCUSBUTTON1, objInst.getname());
}

function btn_messagebox_stop_on_click(objInst)
{
    //
    screen.messagebox("STOP      ", "STOP      ",
        XFD_MB_STOP, XFD_MB_OK, XFD_MB_FOCUSBUTTON1, objInst.getname());
}

// / /
function btn_messagebox_abortretryignore_on_click(objInst)

```

```
{
    screen.messagebox("ABORT/RETRY/IGNORE      ", "ABORT/RETRY/IGNORE      ",
        XFD_MB_QUESTION, XFD_MB_ABORTRETRYIGNORE, XFD_MB_FOCUSBUTTON1,
objInst.getname());
}

function btn_messagebox_ok_on_click(objInst)
{
    //
    screen.messagebox("OK      ", "OK      ",
        XFD_MB_INFORMATION, XFD_MB_OK, XFD_MB_FOCUSBUTTON1,
objInst.getname());
}

function btn_messagebox_okcancel_on_click(objInst)
{
    // /
    screen.messagebox("OK/CANAEL      ", "OK/CANAEL      ",
        XFD_MB_INFORMATION, XFD_MB_OKCANCEL, XFD_MB_FOCUSBUTTON1,
objInst.getname());
}

function btn_messagebox_retrycancel_on_click(objInst)
{
    // /
    screen.messagebox("RETRY/CANCEL      ", "RETRY/CANCEL      ",
        XFD_MB_INFORMATION, XFD_MB_RETRYCANCEL, XFD_MB_FOCUSBUTTON1,
objInst.getname());
}

function btn_messagebox_yesno_on_click(objInst)
{
    // /
    screen.messagebox("YES/NO      ", "YES/NO      ",
        XFD_MB_INFORMATION, XFD_MB_YESNO, XFD_MB_FOCUSBUTTON1,
objInst.getname());
}

function btn_messagebox_yesnocancel_on_click(objInst)
{
    // / /
    screen.messagebox("YES/NO/CANCEL      ", "YES/NO/CANCEL      ",
        XFD_MB_INFORMATION, XFD_MB_YESNOCANCEL, XFD_MB_FOCUSBUTTON1,
objInst.getname());
}

function btn_messagebox_cancelretrycontinue_on_click(objInst)
{
    // / /
    screen.messagebox("CANCEL/RETRY/CONTINUE      ", "CANCEL/RETRY/CONTINUE
",
        XFD_MB_INFORMATION, XFD_MB_CANCELRETRYCONTINUE, XFD_MB_FOCUSBUTTON1,
```

```
objInst.getName());
}

// ( 가 async )
async function btn_messagebox_sync_on_click(objInst)
{
    var messagebox_result;

    factory.consoleprint("messagebox_sync> before call messageboxsync");

    // messageboxsync API "on_messagebox" 가
    // messageboxsync API 가
    // 가 가
    // await async
    messagebox_result = await screen.messageboxsync("
?", " ",
    XFD_MB_QUESTION, XFD_MB_YESNOCANCEL, XFD_MB_FOCUSBUTTON1);

    factory.consoleprint("messagebox_sync> after call messageboxsync");

    factory.consoleprint("messagebox_sync> messagebox_result = " +
messagebox_result);
    factory.consoleprint("messagebox_sync> messagebox_result_type = " +
this.GetMessageBoxType(messagebox_result));
}
```

From:

<https://technet.softbase.co.kr/wiki/> - xFrame5 TechNet

Permanent link:

https://technet.softbase.co.kr/wiki/guide/screen/screen/screen_messagebox



Last update: **2023/08/08 13:35**